

Linux Installation Instructions

DaVinci Resolve 15.2.2

Pre-installation Notes

- DaVinci Resolve for Linux is a free download and does not require a license dongle or an activation
- DaVinci Resolve Studio for Linux supports both the Mac/Windows dongle as well as the Advanced Panel dongle (previously known as the Linux dongle)
- The installer for DaVinci Resolve Studio supports stand alone CentOS/RHEL 7 installations and the legacy Resolve DVD environment (supported by previous versions of Resolve)
- DaVinci Resolve and DaVinci Resolve Studio on Linux support decoding of ProRes media
- Support for ProRes encoding is available in DaVinci Resolve Studio on Linux when using the Advanced Panel dongle
- Currently the RED ROCKET card and driver are not supported on CentOS 7 (will be supported in a future update)

Installation instructions for DaVinci Resolve and DaVinci Resolve Studio software (for the legacy Resolve DVD environment, skip to the next section)

1. Download *DaVinci_Resolve_Studio_15.2.2_Linux.zip* (if you have a DaVinci Resolve license dongle or activation code) or *DaVinci_Resolve_15.2.2_Linux.zip* from the Blackmagic Design website.
2. Unzip the installer by double-clicking the zip file, or by running these commands in Terminal:

```
cd /path/to/downloaded/software/location  
and  
unzip DaVinci_Resolve_Studio_15.2.2_Linux.zip  
or  
unzip DaVinci_Resolve_15.2.2_Linux.zip
```
3. If the downloaded installer does not have executable permissions, you can restore executable permissions from the command line:

```
chmod +x DaVinci_Resolve_Studio_15.2.2_Linux.run  
or  
chmod +x DaVinci_Resolve_15.2.2_Linux.run
```

Please ensure that you are not logged in as root for the installation (either at Desktop login or on the Terminal). Installing Resolve as root may cause issues with file permissions when running Resolve as a non-root user.

4. Installing for CentOS 7:

To install using a GUI based installer, double click the installer file.

Enter the root password when prompted on the GUI and follow the instructions in the installer.

To install from the Terminal, execute the *.run command on the command line and enter the root password when prompted:

```
sudo DaVinci_Resolve_Studio_15.2.2_Linux.run -i  
or  
sudo DaVinci_Resolve_15.2.2_Linux.run -i
```

5. Installing for CentOS 6.8:

To install using a GUI based installer, execute the *.run command on the command line and enter the root password when prompted:

```
sudo DaVinci_Resolve_Studio_15.2.2_Linux.run  
or  
sudo DaVinci_Resolve_15.2.2_Linux.run
```

Follow the instructions in the installer

To install from the Terminal, execute the *.run command on the command line and enter the root password when prompted:

```
sudo DaVinci_Resolve_Studio_15.2.2_Linux.run -i  
or  
sudo DaVinci_Resolve_15.2.2_Linux.run -i
```

On legacy DaVinci Resolve Linux installations with the DVD environment, Resolve can be installed by following the instructions provided below.

1. Download *DaVinci_Resolve_Studio_15.2.2_Linux.zip* file.
2. Double click the zip file to open it and drag *DaVinci_Resolve_Studio_15.2.2_Linux.sh* to the `/home/resolve/Releases/` folder
3. Double-click the installer to install the release from the File Browser

Update instructions for updating the NVIDIA driver

For users who have not yet installed the recommended NVIDIA driver, instructions to update the driver are detailed below. Download the recommended driver from <http://www.nvidia.com/download/driverResults.aspx/131853/en-us> by clicking on "DOWNLOAD" in the provided link. Then, perform the following steps:

1. Open a Terminal shell
2. You need to now become the root user. Type:

```
su -
```


When prompted, please enter your 'root' user's password.
3. You need to disable the Linux desktop and switch to a text interface. Type:

init 3

4. You will be prompted for username to login as. Type:
root
5. Enter your 'root' user's password.
6. Navigate to the folder with the downloaded driver. Type:
cd /path/to/downloaded/driver/location
7. Run the NVIDIA driver installer. Type:
sh NVIDIA-Linux-x86_64-390.42.run --silent --no-network
8. After the script completes, you should see the terminal prompt. Then, reboot the machine. Type:
reboot

Update instructions for updating the DeckLink driver

For users who have not yet installed the latest DeckLink driver, instructions to update your driver are detailed below. Download the latest Desktop Video drivers for Linux from <https://www.blackmagicdesign.com/support/family/capture-and-playback>. Then, perform the following steps:

1. Open a Terminal shell
2. You need to now become the root user. Type:
su -
When prompted, please enter your 'root' user's password.
3. Uninstall the existing driver. Type:
rpm -qa | grep desktopvideo | xargs rpm -e
4. Uncompress the downloaded driver package. Type:
tar xvfz /path/to/downloaded/driver/location/Blackmagic_Desktop_Video_Linux_<driver_version>.tar.gz
5. Install the latest Desktop Video driver. Type:
rpm -ivh Blackmagic_Desktop_Video_Linux_<driver_version>/rpm/x86_64/desktopvideo-<driver_version>.x86_64.rpm
6. After the installation completes, you should see the terminal prompt. Then, reboot the machine.
7. After the machine has rebooted, open a Terminal shell again
8. You need to now become the root user. Type:
su -
When prompted, please enter your 'root' user's password
9. You will now need to update the firmware on your DeckLink card. Type:
BlackmagicFirmwareUpdater update 0
10. If a firmware update was applied, reboot the machine after it completes. If no firmware update was required, a reboot is not necessary.

Update instructions for updating the RED rocket driver (if a RED rocket card is being used)

For users who have not yet installed the recommended RED Rocket driver, instructions to update your driver are detailed below. Download the recommended drivers from http://downloads.blackmagicdesign.com/DaVinciResolve/REDrocket-2.1.23.0_Resolve.tgz. Then, perform the following steps:

1. Open a Terminal shell
2. You need to now become the root user. Type:
su -
When prompted, please enter your 'root' user's password
3. Navigate to the target folder where the driver need to be installed. Type:
cd /usr/local/driver
4. Uncompress the downloaded driver package. Type:
tar xvfz /path/to/REDrocket-2.1.23.0_Resolve.tgz
5. Open the folder with the RED Rocket driver. Type:
cd /usr/local/driver/REDrocket-2.1.23.0
6. Run the driver installation and setup script. Type:
./install_driver.sh
7. After the script completes, you should see the terminal prompt. Then, reboot the machine.
8. After the reboot is complete, open a Terminal shell
9. You need to now become the root user. Type:
su -
When prompted, please enter your 'root' user's password
10. Navigate to the folder where the driver is installed. Type:
cd /usr/local/driver/REDrocket-2.1.23.0
11. You now need to upgrade the firmware on your RED Rocket card(s). Type:
./rocketup_1.1.18.0
12. After the upgrade completes, you should see the terminal prompt. Shutdown the machine entirely. Type:
shutdown -h now
13. After the machine has powered down, restart the machine.

Update instructions for updating the RED RocketX driver (if a RED RocketX card is being used)

For users who have not yet installed the recommended RED RocketX driver, instructions to update your driver are detailed below. Download the recommended drivers from http://downloads.blackmagicdesign.com/DaVinciResolve/REDrocketX-2.1.34.0_Resolve.tgz. Then, perform the following steps:

1. Open a Terminal shell

2. You need to now become the root user. Type:
`su -`
When prompted, please enter your 'root' user's password
3. Navigate to the target folder where the driver need to be installed. Type:
`cd /usr/local/driver`
4. Uncompress the downloaded driver package. Type:
`tar xvfz /path/to/REDrocketX-2.1.34.0_Resolve.tgz`
5. Open the folder with the RED RocketX driver. Type:
`cd /usr/local/driver/REDrocketX-2.1.34.0`
6. Run the driver installation and setup script. Type:
`./install_driver.sh`
7. After the script completes, you should see the terminal prompt. Then, reboot the machine.
8. After the reboot is complete, open a Terminal shell
9. You need to now become the root user. Type:
`su -`
When prompted, please enter your 'root' user's password
10. Navigate to the folder where the driver is installed. Type:
`cd /usr/local/driver/REDrocketX-2.1.34.0`
11. You now need to upgrade the firmware on your RED RocketX card(s). Type:
`./rocketxup_1.4.22.18`
12. After the upgrade completes, you should see the terminal prompt. Shutdown the machine entirely. Type:
`shutdown -h now`
13. After the machine has powered down, restart the machine.

DaVinci Resolve CentOS Installation

For users setting up new systems or wishing to upgrade their DaVinci Resolve system, an ISO of the Resolve Installation DVD with CentOS 7.3 is available to download.

The ISO file for CentOS 7.3 can be downloaded from the following link:

http://downloads.blackmagicdesign.com/DaVinciResolve/DaVinci-Resolve-Linux-15.2-CentOS_7.3.iso

(MD5: http://downloads.blackmagicdesign.com/DaVinciResolve/DaVinci-Resolve-Linux-15.2-CentOS_7.3.txtf).

This ISO file also contains software for DaVinci Resolve and DaVinci Resolve Studio 15.2.

The Automatic configuration option on the DVD will erase all the files on your connected hard disks during installation. Please ensure that you only connect the single hard disk on which you would like to install the OS. To manually configure and select the disks and partitions during the OS installation, please select the Manual configuration option. Please note that you will need to first backup all of your files and Resolve databases externally prior to installing the OS. After the OS installation, you will need to manually restore this data. For more information regarding installation, backup and restoration, please contact your system administrator or DaVinci Resolve Linux reseller.

After completing your OS installation, please remember to check the Blackmagic Design support website for a newer DaVinci Resolve software version.